

LD with Ethernet and SOPAS


: Auto Ident

Sept. 2006




- : Introduction
 - : Product Portfolio BU07
 - : Product Performance Distance
 - : Product Performance Interface
 - : NEWS on LD OEM
 - : Whats new
- : Communication Interfaces
 - : Ethernet data structure
 - : Connections and Pin-out
 - : Hardware connectivity
- : Steps for communication setup
 - : Parameterize LD XXX by SOPAS

Product portfolio BU07



Product Performance Distance



Product Performance Interfaces



Measurement Data only

RS 232; RS 422;
CAN; Ethernet



LMS 4XX - and
LD XX ; LD-LRS

Measurement + Application

RS 232; RS 422



LMS2XX - and
LMS 2XX- S07

Systems

RS 232;
RS 422



Peco, LD PDS,
NAV

: old order numbers:

1023020
1023021
1023022
1023023

Replaced by



NEW Number
1028698

Differences

- ➔ All Interfaces in One Scanner
 - RS232, RS 422 (selectable in the Connection hood)
 - Ethernet
 - CAN
- ➔ SOPAS User Interface
- ➔ 15 PIN Connector



RS 232 or RS 422:

- : up to 115 KBaud
- : 8 data bits
- : 1 Stop bit
- : none parity



CAN 2.0:

- : up to 1 MBaud



Ethernet:

- : 10 MBaud
- : peer-to-peer

: Data structure via Ethernet Interface for realtime measurement


The communication protocol follows the TCP / IP standard. The transferred data is split up into multiple packets. For the programmer this is not relevant. On the receiving end the individual packets are automatically collected and put into the correct sequential order.

The connection will be established via the **Port 49152**



Ethernet selection
screen in OPAS

: Data structure via Ethernet Interface for realtime measurement



STX „Start of Text“, will be transferred as a single byte, 0x02.

MRK Definition of the transmission format „USP“= 0x55, 0x53, 0x50 (3 Bytes),

LEN UPF-Length = the number of following bytes in <data>, coded as 32-Bit-Integer (four bytes) without leading sign; the msb (most significant byte) must be transmitted first of all.

CS Checksum, is a single byte, calculated as exclusive-or-relation of all bytes contained in „Data“.

Service Code and Service Data are conform to format that is described in the telegram listing of the LD OEM.




Ethernet
selection screen
in SOPAS


Ethernet Data Structure



- : Data structure via Ethernet Interface
- : Example : Request for status



Connections and Pin-out



Connections and Pin-out



Pin assignment in 15-pin D-sub plug (high-density)


Pin	Signal				Function
1	V-EXT				Voltage supply, sensor (24VDC)
2	CAN L				CAN bus (IN/OUT)
3	CAN H				CAN bus (IN/OUT)
4	Signal GND				Ground
5	GND EXT				Ground, sensor
6	RS-422	RD_HST+	RS-232	Not occupied	Host interface (receiver)
7		RD_HST-		RxD_HST	
8		TD_HST+		Not occupied	Host interface (transmitter)
9		TD_HST-		TxD_HST	
10	OUT 1				Output 1
11	TPIP				Ethernet interface IN
12	TPIN				Ethernet interface IN
13	TPOP				Ethernet interface OUT
14	TPON				Ethernet interface OUT
15	OUT 2				Output 2



Connections and Pin-out



Power supply



Steps for communication setup








- : Connect Hardware
- : Parameterize LD XXX
- : Send measurement commands to LD XXX
- : Receive scans and process


Parameterize LD XXX by SOPAS




(for simplicity use Terminal RS 232 connection):

-  : Start SOPAS Software with new project
-  : Select interface and scan for device
-  : Login and change user Level
-  : Change basic parameters
-  : Scan profiles

Start SOPAS with new project




Start SOPAS with new project



SOPAS Start up screen




Select interface and scan for device




Serial interface selection screen

Select interface and scan for device




Serial interface advanced selection screen

Select interface and scan for device




Ethernet selection screen

Select interface and scan for device




Scanner found and matching

Select interface and scan for device



Add device


Select interface and scan for device




LD XXX connected and synchronized



Login to device and change user level



Login to device and change user level




Select user level

Select user level and
put in password 'client'
(request initial password from SICK)




Change basic parameters




Set angular range

Change basic parameters




Set scan frequency

Change basic parameters




Set scan resolution

Change basic parameters




Check the result box if settings valid

Change basic parameters



Download parameters if “Download on demand is selected”


Change basic parameters



Save Parameters permanently in LD-OEM



Scan profiles



SICK

Thank you
for your attention!